

## Procedure to upgrade EZ-Guide

You will need the 18352 cable that came with your EZ-Guide system. You will also need to be able to power you light bar with 12VDC while it is connected to your computer.

### Download Firmware and Toolbox program

1. Select to following link  
[EZ-Guide Support](http://www.ez-guide.com/ezguideplus_ts2.asp)  
[http://www.ez-guide.com/ezguideplus\\_ts2.asp](http://www.ez-guide.com/ezguideplus_ts2.asp)
2. Click on EZ-Guide Plus current firmware
3. Click on EZ-Guide Plus 4.10 to download the current firmware.
4. Save the firmware in a folder that you can access later.
5. Select the following link  
[EZ-Guide Support](http://www.ez-guide.com/ezguideplus_ts2.asp)  
[http://www.ez-guide.com/ezguideplus\\_ts2.asp](http://www.ez-guide.com/ezguideplus_ts2.asp)
6. Click on EZ-Toolbar
7. Click on EZ-Toolbar 2.10
8. Click RUN
9. Follow the steps in the toolbox setup wizard to install toolbox.

### Upgrade Lightbar

1. Connect 18532 cable to your laptop COM1 port and to the serial connector on the lighthbar
2. Disconnect power to lighthbar
3. Click EZ-Toolbar icon on your computer desktop.
4. Click EZ-Guide + tab.
5. Click browse and find folder you saved firmware in earlier.
6. Click on folder and click OK
7. Click Proceed and follow instructions to complete upgrade.